

SafeUEM Datasheet



Full Lifecycle Enterprise Mobile Management

Device Enrollment

Scan a group QR code or enrollment password to enroll devices



Function Management

- Disabling Wi-Fi, camera, or Bluetooth
- Pushing APN settings
- Assigning Kiosk mode




Application Management

- App blacklist & whitelist
- Pushing apps to devices
- Silent installation
- Enterprise app store



Content Management

- Pushing data to specified devices
- Uploading logs to the server
- Creating a secured Enterprise folder in the devices



Network Management

- Firewall, a blacklist of network access
- Safe browser, blacklist or whitelist of websites



Behavior Management

- Geo Fence, allowing devices to be used in specific geographic areas

Device Recycle

End a device lifespan or start a new cycle. For example, a device is lost.



System Deployment

SaaS (Cloud) Deployment vs On Premise Installation

Items	SaaS (Cloud)	On Premise Installation
Hosts	AWS	Customer site
Capability	Manage up to 500K devices	Manage up to 100K devices
Storage (per 1000 license)	5GB DB + 5GB disk space	Customer decision
Network Bandwidth	Shared network bandwidth	Customer decision
Maintenance	SafeUEM	Customer
Technical Support	Online Support	Online Support
Price	License + Cloud maintenance	License only

On Premise Installation Requirements

Items	SMB	Enterprise I	Enterprise II
Device Count	< 1,000	> 1,000 and < 5,000	> 5,000 and < 20,000
Number of Servers	1	2	3-4
CPU	quad core 2.5 GHz	quad core 2.5 GHz	quad core 2.5 GHz
Memory	8 GB	8 GB	8 GB
Disk Space	100 GB	500 GB	500 GB
Network	1 static Internet IP address or domain name, 5MB-10MB bandwidth	1 static Internet IP address or domain name, 10MB-20MB bandwidth	1 static Internet IP address or domain name, 20MB-50MB bandwidth
Operating System	Windows Server 2012 R2 up or Linux Ubuntu v16 up	Linux Ubuntu v16 up	Linux Ubuntu v16 up

System Network Architecture

